

# **German Oktoberfest**

Amber in color with a nice blend of Munich malt and crystal grains. Medium-bodied, malty and finished with a distinct hop flavor. This kit includes a lager yeast that will also perform well if fermented at ale temperatures.

OG: 1.052 - 1.056 FG: 1.013 - 1.016 IBUs: 21 - 24 ABV: 5.25% - 5.75% Difficulty: Intermediate Color: Amber

## Contents

- Ingredients Priming Sugar
- Grain Bag(s)
   Bottle Caps
  - Brewing Procedures

Hops may vary due to availability.

# **Glossary DME**

Original Gravity

**LME IBU** 

Specific Gravity Liquid Malt Extract

FG

Final Gravity CO2 Carbon Dioxide

Units (Tinseth) **ABV** 

Alcohol by Volume

International Bittering

**Dried Malt Extract** 

## **Ingredients**

**FERMENTABLES** 

6.6 lb. Amber LME

1 lb. Amber DME

SPECIALTY GRAINS

8 oz. Cara Munich Dark

4 oz. Cara Red

6 oz. Munich Light

**HOPS** 

2 packs 1 oz. Northern Brewer

YEAST

1 Sachet

# **Recommended Procedures**

NOTE: This is a lager recipe and includes lagering procedures which require special temperature-controlled conditions.

BREW DAY (DATE \_\_/\_\_)

## 1. READ

Read all of the recommended procedures before you begin.

## 2. SANITIZE

Thoroughly clean and sanitize ALL brewing equipment and utensils that will come in contact with any ingredients, wort or beer with a certified sanitizer, e.g., Star San or IO Star.

# 3. STEEP GRAINS

Pour 2.5 gallons of clean water into your brew pot and begin to heat1. Pour crushed grains into grain bag and tie a loose knot at the top of the bag<sup>2</sup>. When the water is within an appropriate steeping temperature (150° - 165°F) place the grain bag into the brew pot<sup>3</sup>. Steep grains for approximately 20 minutes. Remove grain bag and without squeezing, allow liquid to drain back into brew pot. Your water is now wort.

#### 4. START BOIL

Bring your wort to a gentle, rolling boil. Add ALL of the LME and DME to the boiling wort4. Continuously stir the extract into the wort as it returns to a gentle, rolling boil<sup>5</sup>.

## 5. FOLLOW SCHEDULE<sup>6</sup>

As directed on the BREW DAY SCHEDULE (right), slowly sprinkle the hops into the boiling wort. Be careful not to let the wort boil over the pot. Using the provided BREW DAY SCHEDULE, note the time the hops were added to help keep your brew on schedule. Continue the gentle, rolling boil until the boil is complete.

Find us on
Facebook

Recommend	<u>led Bre</u>	w Day	<u>Equip</u>	<u>omen</u>

- 4 Gallon Brew Pot (or larger)
- 6.5 Gallon Fermenter
- Airlock

Long Spoon or Paddle

- Hydrometer
- Thermometer
- No-Rinse Sanitizer
- Cleanser

## **Brew Tips**

<sup>1</sup>We suggest doing a 2.5 gallon boil at minimum. If you have the equipment to boil more than 2.5 gallons feel free to do so. There is no need to change the amount of any of the ingredients.

<sup>2</sup>The grains should not be compacted inside the bag. Grains should steep loosely allowing the hot water to soak into all of the grain evenly.

<sup>3</sup>Pay careful attention not to let your steeping water exceed 170°F which leeches tannins into the wort.

<sup>4</sup>Run canisters of LME under hot water to allow the extract to pour easier.

<sup>5</sup>Pay careful attention that the extract does not accumulate and caramelize on the bottom of your brew pot.

<sup>6</sup>When consumed, hops can cause malignant hyperthermia in dogs, sometimes with fatal results. Even small amounts, including "spent" hops from brewing, can trigger a deadly reaction.

<b>BREW DAY SCHEDULE</b>	BRI	EW	DAY	SCH	<b>EDI</b>	JLE
--------------------------	-----	----	-----	-----	------------	-----

1.	Add bo	oth 1 (	oz. pac	ks Nort	thern B	rewer l	hops
----	--------	---------	---------	---------	---------	---------	------

(time)

2. Boil 60 minutes

3. Terminate boil (time)

> **Total Boil Time: 60 minutes** Continue to Step #6

# Recommended Procedures (continued)

# 6. COOL WORT & TRANSFER

Cool the wort down to approximately 60°F by placing the brew pot in a sink filled with ice water<sup>7</sup>. Pour or siphon wort into a sanitized fermenter. Avoid transferring the heavy sediment (trub) from the brew pot to the fermenter.

## 7. ADD WATER

Add enough clean water (approx. 50° - 60°F) to the fermenter to bring your wort to approximately 5 gallons<sup>8</sup>. Thoroughly stir the water into the wort. Using a sanitized hydrometer take an Original Gravity (OG) reading. Once you are satisfied your wort is at the proper volume and within the OG range, record the OG in the ABV% CALCULATOR (right).

## 8. PITCH YEAST

Sprinkle the contents of the yeast sachet (DO NOT REHYDRATE) over top of the entire wort surface and stir well with a sanitized spoon or paddle. Firmly secure the lid onto the fermenter. Fill your airlock halfway with water and gently twist the airlock into the grommeted lid. Move the fermenter to a cool, lager-specific, **temperature-stable area** (approx. 53° - 59°F).

# **FERMENTATION**

## 9. PRIMARY

The wort will begin to ferment within 24 - 48 hours and you may notice CO2 releasing (bubbling) out of the airlock. If no bubbling is evident on day two of fermentation, take a gravity reading with a sanitized hydrometer. If gravity has dropped below your OG reading then fermentation is taking place. Take a gravity reading again in 10 - 14 days and confirm fermentation has completed by comparing the gravity reading to the FG range listed at the top of the instructions. If gravity is not in the FG range, continue fermentation until it reaches the FG range. Record your FG reading in the ABV% CALCULATOR (right).

## 10. SECONDARY/LAGERING9

Transfer the beer to a clean, sanitized 5-gallon carboy. Lower the temperature 1° to 3° per day until it reaches 35° - 42°F¹0. Lager within this temperature range 3 - 4 weeks. If you don't have equipment for lagering see "Brewed As An Ale" right. After lagering is complete proceed to bottling day.

# BOTTLING DAY (DATE / / )

#### 11. READ

Read all of the recommended procedures before you begin.

## 12. SANITIZE

Thoroughly clean and sanitize ALL brewing equipment, utensils, and bottles that will come in contact with any ingredients, wort or beer with a certified sanitizer, e.g., Star San or IO Star.

## 13. PREPARE PRIMING SUGAR

In a small saucepan dissolve 4 oz. of priming sugar into 2 cups of boiling water for 5 minutes. Pour this mixture into a clean bottling bucket. Carefully siphon beer from the fermenter to a bottling bucket. Avoid transferring any sediment. Stir gently for about a minute. 1 oz. of priming sugar is equal to 2.5 tablespoons.

## 14. BOTTLE

Using your siphon setup and bottling wand, fill the bottles<sup>11</sup> to within approximately one inch of the top of the bottle. Use a bottle capper to apply sanitized crown caps.

## 15. BOTTLE CONDITION

Move the bottles to a dark, warm, **temperature-stable** area (approx. 64° - 72°F). Over the next two weeks the bottles will naturally carbonate. Carbonation times vary depending on the temperature and beer style, so be patient if it takes a week or so longer.

# CHILL & ENJOY YOUR TASTY BREW AND THANK YOU FOR CHOOSING BREWER'S BEST® PRODUCTS.

## **Brew Tips**

<sup>7</sup>To avoid bacteria growth do this as rapidly as possible. Do not add ice directly to the wort. Alternatively, you can use a brewing accessory like a Wort Chiller.

<sup>8</sup>Be careful not to add a volume of water that will cause the wort to fall outside of the OG range specified in the BREW STATS.

<sup>9</sup>Before proceeding to the lager stage be sure the beer is in your secondary fermenter and has reached its FG, then begin lowering the temperature as indicated in Step #10.

<sup>10</sup>Filling your airlock with distilled spirits will prevent it form freezing.

<sup>11</sup>Use standard crown bottles, preferably amber color. Make sure bottles are thoroughly clean. Use a bottle brush if necessary to remove stubborn deposits. Bottles should be sanitized prior to filling.

# **Brewed As An Ale**

Brewer's Best® recommends lagering this recipe to achieve the true lager character of this beer style. However, if you are not properly equipped to lager your beer, the included yeast will perform well when fermented as an ale. When fermenting as an ale (between 64° - 72°F) try to keep the beer on the cooler end of the temperature range and allow for some additional time for the lager yeast to ferment down to the FG. If possible, rack to a secondary fermenter for two weeks prior to bottling. Consult your local homebrew shop to learn more about the equipment necessary to lager your beers. Although this method is not as accurate as temperature-controlled lagering equipment, most climates provide a seasonal window that will allow you to lager beer.

# Recommended Bottling Day Equipment

- 6.5 Gallon Bottling Bucket Bottle Brush
- Siphon Setup
- Capper
- Bottle Filling Wand
- Sanitizer
- 12 oz. Bottles (approx. 53)
- Brewer's Best® Crown Caps

# **ABV% Calculator**

(OG - FG) x 131.25 = ABV% (\_\_\_\_\_\* - \_\_\_\_\*\*) x 131.25 = \_\_\_\_

\*OG from Step #7
\*\*FG from Step #9

